


>>> Self-help Guide <<<


### Configure SMU Wi-Fi (WLAN-SMU)

Reference OS: Windows 8.1


1. At the Metro Screen, press the **windows** key on your keyboard together with the alphabets “**X**” to go to the Control Panel.




2. In the Control Panel window, click on “**Network and Internet**”.



3. In the Network and Internet windows, click on “**Network and Sharing Center**”.




4. In Network and Sharing Center windows, click on “**Set up a new connection or network**”.




5. Next, click on “**Manually connect to a wireless network**”.

Choose a connection option




6. When prompted to enter the wireless network information:
  - Enter the Network name/SSID:  
**WLAN-SMU**
  - Select “**WPA2-Enterprise**” as the Security Type. Encryption type will be defaulted to **AES**.
  - Enable the “**Start this connection automatically**” check box.
  - Enable the “**Connect even if the network is not broadcasting**” checkbox.
  - Click “**Next**” button.

## Configure SMU Wi-Fi (WLAN-SMU) : Not-Joined Domain




7. In the next window, click on “**Change connection settings**”.

Successfully added WLAN-SMU




8. In the pop-up window, **Wireless Network Properties**:

- Click on the “**Security**” tab.




9. Under the **Security** options:

- Click on the “**Settings**” button.




10. In the Protected EAP Properties page:

- Uncheck “**Validate server certificate**”.
- Click on the “**Configure...**” button.




## Configure SMU Wi-Fi (WLAN-SMU) : Not-Joined Domain

- Uncheck the “Automatically use my Windows login name and password” and click on **OK** button.




- Ensure the checkbox for “Specify authentication mode:” is checked.
- From dropdown menu, select “User authentication”.




### 11. Under the **Security** options:


- Click on the “Advanced settings”.



- Click on the “Save credentials” button.



- Enter your SMU username and password and click on “OK” button.



- From “Wireless Network Properties” windows, click on “OK” to finish the configuration.

## Configure SMU Wi-Fi (WLAN-SMU) : Not-Joined Domain

- Click on the wireless connection icon as shown in the diagram to view the status of the wireless access.



- When you are within range of the Wireless Access Point and your wireless network radio enabled, Windows will display a “**Connected**” message.

